

Quassel IRC - Bug #495

storage location of quasselclient.conf is not configurable

01/21/2009 07:42 PM - billie

Status:	Rejected	Start date:	01/21/2009
Priority:	Normal	Due date:	
Assignee:	Sputnick	% Done:	80%
Category:	Quassel Client	Estimated time:	0.00 hour
Target version:	0.4.0	OS:	Any
Version:	0.3.1+		
Description			
After changing the default location for configuration files quasselcore.conf successfully migrated to the customized --configdir. quasselclient.conf always stays at the new default location ~/.config/quassel-irc.org regardless of the --configdir setting.			

History

#1 - 01/22/2009 08:34 PM - Sputnick

- Status changed from New to Feedback

- Target version set to 0.4.0

- % Done changed from 0 to 80

Works for me:

```
sputnick@axion tbuild % ./quassel --configdir=~/.tmp/fubar
```

```
*** IMPORTANT: Config and data file locations have changed. Attempting to auto-migrate your client settings...
* Your client settings have been migrated to "/home/sputnick/tmp/fubar/quasselclient.conf"
*** Migration completed.
```

```
2009-01-22 20:32:06 Warning: SslServer: Certificate file /home/sputnick/tmp/fubar/quasselCert.pem does not exist
```

```
2009-01-22 20:32:06 Warning: SslServer: Unable to set certificate file
Quassel Core will still work, but cannot provide SSL for client connections.
Please see http://quassel-irc.org/faq/cert to learn how to enable SSL support.
```

```
2009-01-22 20:32:06 Warning: SslServer: Certificate file /home/sputnick/tmp/fubar/quasselCert.pem does not exist
```

```
*** IMPORTANT: Config and data file locations have changed. Attempting to auto-migrate your core settings...
* Your core settings have been migrated to "/home/sputnick/tmp/fubar/quasselcore.conf"
* Your database has been moved to "/home/sputnick/tmp/fubar/quassel-storage.sqlite"
*** Migration completed.
```

```
2009-01-22 20:32:06 Info: Storage Backend is ready. Quassel Schema Version: 13
```

```
2009-01-22 20:32:06 Info: Restoring previous core state...
```

```
sputnick@axion tbuild % ls ~/.tmp/fubar
quasselclient.conf quasselcore.conf quassel-storage.sqlite
sputnick@axion tbuild %
```

Please try again and make sure you did nothing wrong; if it still fails, please describe exactly what you did. Migration code for core and client settings is identically, and they both use `Quassel::configDirPath()` to determine the new files' location, so I don't see how this could fail, and I obviously can't reproduce.

#2 - 01/22/2009 09:26 PM - billie

1. Stop core

2. Move files (quasselCert.pem quasselclient.conf quasselcore.conf quassel-storage.sqlite) to `./tmp/fubar`

3. Start core with `"quasselcore --configdir=./tmp/fubar"`

4. All files are recognized in the location for configdir passed to quasselcore besides quasselclient.conf which is ignored and created at `~/.config/quassel-irc.org`

5. Getting almost kick-banned on a few channels after doing this ten times within 15 minutes ;-)

#3 - 01/22/2009 10:30 PM - Sputnick

Can you tell me what's in that file that gets created? I have a feeling that it's quite empty...

#4 - 01/23/2009 11:27 PM - Sputnik

- *Status changed from Feedback to Rejected*

Error on layer 8.